





## **AVID Liquid 7.x** **Активация без подключения системы к сети** **Интернет**

При каждом запуске Liquid будет появляться следующее окно. Щелкните по кнопке “Activate Now” (активировать сейчас).




В следующем окне щелкните по кнопке “View Instructions” (ознакомиться с инструкциями).



В данном окне будет отображена вся необходимая информация, мы рекомендуем распечатать это окно, нажав кнопку “Print this information”. Затем щелкните по кнопке “I do not wish to activate this

feature at this time” (я не буду сейчас активировать данную возможность) и закройте программу Liquid.



Затем на компьютере, имеющем доступ к Интернет, зайдите на страничку <http://www.avid.com/activate>. Заполните все соответствующие поля. Будьте осторожны и не перепутайте ноль (0) с заглавной буквой О. Обязательно укажите адрес реально существующего ящика электронной почты.



## Premium Content



> **Questions About Unlock**  
If so, Click Here!

### Helpful Links

- > **Questions About Unlock**
- > **Privacy Policy**
- > **Security Information**
- > **Order History**
- > **Lost Your Key?**

### Welcome,

This site will guide you through purchasing an Activation Key that will enable premium content packs or premium features inside your application.

### Pinnacle Systems Product Selection:

Please select a product for which you wish to purchase an Activation Key. If you are not sure which product you are using, go to the Help menu in your application and select "About".

- |  |  |   |
|--|--|---|
| <input type="radio"/> Studio 10 Plus (30001)       | <input type="radio"/> Avid Liquid 7 (40001)                | <input type="radio"/> Instant PhotoAlbum (1432)       |
| <input type="radio"/> Studio 10 (30002)            | <input checked="" type="radio"/> Avid Liquid PRO 7 (40002) | <input type="radio"/> ShowCenter (1481)               |
| <input type="radio"/> Studio 10 SE (30003)         | <input type="radio"/> Avid Liquid 7 AV/DV (40003)          | <input type="radio"/> PCTV v5 (6)                     |
| <input type="radio"/> Studio 10 QuickStart (30004) | <input type="radio"/> Avid Liquid Chrome HD v7 (40004)     | <input type="radio"/> PCTV Stereo v5 (1480)           |
| <input type="radio"/> Studio Plus 10 Trial (30005) | <input type="radio"/> Liquid Edition v6 (2452)             | <input type="radio"/> PCTVpro v5 (103)                |
| <input type="radio"/> Studio Plus v9 (2446)        | <input type="radio"/> Liquid Edition Pro v3 (2480)         | <input type="radio"/> PCTV USB2 v5 (2123)             |
| <input type="radio"/> Studio v9 (1501)             | <input type="radio"/> Liquid Edition AV/DV v6 (22007)      | <input type="radio"/> Pinnacle Media Center 4 (40005) |
| <input type="radio"/> Studio QuickStart v9 (2118)  | <input type="radio"/> HFX Plus for Liquid/Edition          | <input type="radio"/> TV Center 4 (40006)             |
| <input type="radio"/> Studio SE v9 (2119)          | <input type="radio"/> HFX PRO for Liquid/Edition           |   |
| <input type="radio"/> Studio Trial v9 (2120)       |  |   |

### Passport

Your Passport is a unique code tied to your application. This code is required to generate your Activation Key(s). If you do not have this information handy, go to the Help menu in your application and click on "My Passport." If you are activating Avid Liquid, please go to the Help menu and click on About Avid Liquid.

Passport:  -  -  -  -

### User Information Needed

Please enter the information below **EXACTLY** as it appears on your registration print-out.

Serial Number:  -  -  -  -

First Name:

Last Name:

Email Address: \*

Country of Purchase:


Preferred Language:

\*Note: this email address will be used to send you your keys once you make your purchase.

**Submit**

В следующем окне щелкните по ссылке „View Catalog Page“.

# Avid



## Premium Content

**Questions About Unlock**  
If so, Click Here!

### Avid Liquid PRO 7

**Helpful Links**

- ▶ **Questions About Unlock**
- ▶ **Privacy Policy**
- ▶ **Security Information**
- ▶ **Order History**
- ▶ **Lost Your Key?**

**Premium Content for Avid Liquid PRO 7**

To begin please select from one of the premium content categories below:

**Instant Activation:**

[View Catalog Page >>](#)

Ключ активации будет доступен в следующем окне, мы рекомендуем вам распечатать его, нажав на кнопку "Print this information".

# Avid



## Premium Content



### > Questions About Unlock

If so, Click Here!

#### Helpful Links

- > [Questions About Unlock](#)
- > [Privacy Policy](#)
- > [Security Information](#)
- > [Order History](#)
- > [Lost Your Key?](#)

## Avid Liquid PRO 7

1. Print or write down the activation key(s).
2. On the computer with Avid Liquid PRO 7, you will need to launch the Avid Liquid PRO 7 application. If the application is running, exit the application.
3. As the application starts up, a dialog box appears. Click on the "Activate Now" button.
4. Enter you activation key in the appropriate field.
5. Launch Avid Liquid PRO 7 and your software is now activated.

Liquid Edition PRO 7 Activation

Don't forget to Register! It only takes a few minutes..

### Register Now!

Register your Avid product now and receive these valuable benefits FREE!:

- **Product Updates and Downloads:** As new software revisions, plug-ins, beta programs, and demo software become available, you'll be notified immediately.
- **Technical Web Support:** Do you have questions about how to use one of our products? Email us anytime 24 hours a day, using our free technical web support. And you'll also have access to our fully searchable Frequently Asked Questions (FAQ) database.
- **Community Support:** Register now and you'll also get free use of our community message boards. Ask questions, make suggestions, and share new ideas with thousands of users worldwide.
- **Special Offers:** Register now and check to see if you are eligible for even more great software add-ons: Free Hollywood FX filters, Auto Color Correction tools, additional DVD menu templates and more!


[Print this information](#)

[Close Window](#)

Запустите Liquid, снова появится окно активации. Щелкните по кнопке “Activate Now” (активировать сейчас).




В появившемся окне щелкните по кнопке „View Instructions“ (ознакомиться с инструкциями).



В следующем окне щелкните по кнопке „Enter Activation Key“ (ввести ключ активации).

**Activate Avid Liquid 7 Activation from another computer** ✕

 You can obtain an Activation Key from another computer by following these instructions.

1. Print out or write down the information below.
2. On your computer with Internet access, point the web browser to <http://www.avid.com/activate>
3. Enter the following information on the activation web page.


URL: <http://www.avid.com/activate>

Product: Avid Liquid 7.1C (40002)


Pinnacle Passport:  
Serial Number:

4. The activation page will generate an Activation Key. Print or write down the Activation Key.
5. On this computer click on the 'Enter Activation Key' below  
(or select 'Enter Activation Keys' from the Avid Liquid 7.10 Help menu).
6. Enter the Activation Key in the dialog box.

Введите ключ активации и щелкните по кнопке „ОК“.



Вы должны будете увидеть сообщение о том, что программа Liquid разблокирована. Подтвердите данное сообщение, щелкнув по кнопке “ОК”.



**Возможные проблемы и их решения:**

- Вы не указали адрес электронной почты.
- Вы ошиблись при вводе каких-либо данных.
- Ничего не происходит, когда вы выбираете *Windows Start (Пуск) – Programme (программы) – Avid Liquid – Online Registration*.
- Срок (30 дней), до истечения которого нужно выполнить активацию программы, истек.
- Вы произвели апгрейд программы, но при этом использовали некорректный CD-диск.
- Вы произвели апгрейд программы, но при этом использовали неверный серийный номер.
- Установите AVID Liquid Upgrade Patch до установки самой программы Liquid. Затем установите последний Liquid Servicepack. Все это вы можете скачать на сайте <http://www.avid.com/onlinesupport/supportcenter.asp?productID=174>.
- Используйте Internet Explorer 6.0 или более старшую версию, очистите кэш и удалите все Cookies; проверьте настройки защиты и настройки firewall.
- После того как программа Liquid перешла в демо-режим, она должна быть деинсталлирована и установлена заново.